## Setting up your Drexel Account on Android

1	2	3
Open the Android Email app and tap Add New Account if it's your first account.	Enter your abc123@drexel.edu email address and your password and click Manual Setup	Select Microsoft Exchange Activesync
Or, got to <b>More</b> > <b>Setting</b> in the app and select <b>Add account</b> and then <b>Add New Account</b>	MANUAL SETUP SIGN IN	

## 4

In the **Domain**\username field, enter your abc123@drexel.edu Drexel email address. In the **Exchange server**, enter **outlook.office365.com** and sign in

000	ount
	Email address abc123@drexel.edu
	Domain\username abc123@drexel.edu
	Password
	Show password
rv	er settings
Е 0	xchange server utlook.office365.com
~	Use secure connection (SSL)
	Use client certificate
	SIGN IN
re	emote server may request certain

Choose your sync settings for your Android device and tap **Sign in**.

6

🔲 🖻 🔰 💐 🕅 76% 🛢 9:15 AM	password on yo
← Manual setup	complete the se
Period to sync Email	← Device a
3 days ▼	Em Em
Sync schedule Auto (when received)	Server outloo to remotely o your device.
Emails retrieval size	Activating ad perform the f
50 KB 💌	Erase a     Erase the     performin
Period to sync Calendar 2 weeks	Set pas Control th allowed i
<ul> <li>Notify me when email arrives</li> <li>Sync Contacts</li> </ul>	Monito     Monitor t     typed. w     the phone     too many
Sync Calendar	Lock th Control h
Sync Task	Set loc     expirat
SIGN IN	CANCEL
	Enter your accorproceed. You'r

## 6

Activate your device administrator. If you do not have a password set up, you will be required to set up a 6 (or more) character password on your Android device to complete the set up.

		S and 76% ■ 9:15 AN
÷	Device adminis	trator
(	Email	
Se to yc	erver outlook.office36 remotely control som our device.	5.com must be able ne security features on
Ac	ctivating administrator erform the following o	r will allow Email to perations:
•	Erase all data Erase the phone's da performing a factor	ata without warning by y data reset.
•	Set password re Control the length a allowed in screen-ur	ules nd the characters nlock passwords.
•	Monitor screen Monitor the number typed. when unlocki the phone or erase a too many incorrect	-unlock attempts of incorrect passwords ing the screen, and lock all the phone's data if passwords are typed.
•	Lock the screen Control how and wh	<b>n</b> ien the screen locks.
•	Set lock-screer expiration	n password
	CANCEL	ACTIVATE